Al Alt Text Image Generator

User Guide

Installation Instructions

Installation via Composer (when purchased in the marketplace)

1. Open your command line terminal, go to your Magento root directory and run the following commands:

composer require remmote/magento2-altreadable
bin/magento setup:upgrade
bin/magento cache:flush

Manual installation (zip file)

- 1. Extract the content of the zip file and upload it to your Magento root installation folder. In case you are asked to merge or replace any files, choose to MERGE the files.
- 2. Open your command line terminal, go to your Magento root directory and run the following commands:

bin/magento setup:upgrade
bin/magento cache:flush

Note:

Magento Cron needs to be running correctly for this extension to work correctly.

Configuration instructions

General configurations

To get started with Al-generated review summaries, head to:

 $Admin\ Panel \to Stores \to Configuration \to Remmote\ Extensions \to AltReadable$

Below is an explanation of each setting in the **General Configuration** section:

Module enabled

Enable or disable the extension

Generate ALT automatically for new images

If YES, a cron job running in the background every day at 2am will generate the ALT text for recently updated products that are missing an ALT Text.

Generate ALTs using product information for context

If YES, the product information is used for context. This will enhance the ALT text for Als and screen readers.

API Configurations

This section lets you control how the AI generates summaries based on customer reviews. You can choose the model and customize the AI's behavior using templates.

API Endpoint URL

The API endpoint to generate ALT texts. Use the default value if you don't have a custom plan.

Test API Endpoint URL

The API endpoint to validate the credentials and check the status of the current plan. Use the default value if you don't have a custom plan.

API Key

Your unique API Keys. Login to <u>altreadable.com</u> to generate you API Keys:



Check credits

Click this button to get the number of credits available for your account. Each one represents one credit.



Check your current API credits and plan information.

Generate ALT Text

Click this button to generate ALT text for images that don't have an ALT text. If you are generating the images for the first time, you can optionally override the existing ALT text for your images.



- This action will process all product images that don't have ALT text
- This process will run in the background and you will receive a notification when it's completed.
 The